

# StagePilotPro V3 – Installation Guide

This guide describes the installation and setup of **StagePilotPro**, consisting of:

- **REAPER**
- **StagePilotPro Control**
- **StagePilot Editor**
- **Singer View**
- **Lyrics Server (Swift)**

The components are deliberately separated to ensure maximum stability and clear responsibilities during live operation.

## 1) License & Activation (after purchase)

After purchase, you will receive an **activation code by email**.

- **One activation per license**
- Activation is performed on the **main computer**  
(the computer running REAPER and the Lyrics Server)

 Control devices (phones, tablets, additional computers) **do not require activation**. They are **not licensed**, only **physically limited by your network**.

Typical parallel usage:

- Singer (Singer View)
- Guitarist (Singer View)
- Technician (Control)
- Bassist (Singer View)

 **Whoever selects or controls a song first effectively determines the state**  
(there is intentionally no user or permission system).

## 2) Requirements

### Hardware

- macOS computer (main system)
- iPhone / iPad / tablet / additional computers (optional)
- Local network (LAN or Wi-Fi)

### Software

- **REAPER** (latest version recommended)
- **REAPER Web Control** enabled
- **StagePilotPro Lyrics Server (Swift app)**
- Modern web browser (Safari, Chrome, Edge)

## 3) Network – fundamental requirement (very important)

**All devices must be on the same network**

**All devices must be connected to the same network.**

This includes:

- Main computer (REAPER + Lyrics Server)
- Phones / tablets (Singer, Control)
- Additional control computers

 **Different Wi-Fi networks or mobile data will not work.**

**Live operation (strongly recommended)**

For live shows, using a **dedicated router** is strongly recommended:

- stable
- offline
- independent of venue networks
- reproducible at every gig

 **No internet connection is required.**

## 4) Preparing REAPER

### 4.1 Install REAPER

- Install and launch REAPER as usual

### 4.2 Enable Web Control

In REAPER:

1. **Options → Preferences**
2. **Control/OSC/Web**
3. **Add → Web Browser Interface**
4. Enable the interface
5. Note the port (default: **8081**)

→ REAPER is now controllable via the network.

## 5) Creating regions in REAPER (core foundation)

StagePilotPro is entirely based on **REAPER Regions**.

- Each song = **one region**
- **Region number** = song order
- **Region name** = Song ID

### Example

REAPER region:

**R1 – Vergessener Traum**

→ This exact spelling will later be used in the Editor.

## 6) Install & start the StagePilotPro Lyrics Server

1. Launch the StagePilotPro Lyrics Server app
2. On first launch:
  - The server starts automatically on **port 8765**
  - The folder  
Documents/lyrics/  
is used automatically

This folder contains:

- all song files (\*.json)
- all Editor save data

 **The server must be running** for Control, Editor and Singer to work.

## 7) Install StagePilotPro Control (REAPER webroot)

In the installer window:

1. Click **Select Webroot...**
2. Choose the REAPER webroot folder
3. Click **Install stagepilotpro.html**

 StagePilotPro Control is now installed directly into REAPER.

## 8) Links, QR codes & Open buttons (central hub)

After installation, the installer shows:

- **StagePilot (REAPER / Control)**
- **Editor (Lyrics Server)**
- **Singer (Lyrics)**

Each with:

- **QR code** (for phone / tablet)
- **Open button** (for the main computer)
- **Copy button** (to share the link)

### Using on the main computer

- Simply click **Open**  
 The corresponding view opens directly in the browser.

### Using on mobile devices

- Scan the QR code with the camera  
 No app, no installation required.

## 9) Network changes & QR codes (important!)

If the network changes, for example:

- different router
- different Wi-Fi
- new IP address of the main computer

 **The QR codes must be updated.**

In the installer:

- click **Update**
- rescan the new QR codes

 **Updating QR codes is often forgotten in live situations**  
and is one of the most common causes of connection issues.

## 10) Launching Editor & Singer

### Control

- Via the REAPER web interface  
or
- via **Open** or QR code

### Editor

- Click **Editor** in Control  
or open directly:

<http://<IP>:8765/editor>

### Singer

- Click **Singer** in Control
- automatically via **Auto Singer**
- or via QR code

All connections are configured automatically  
(server + REAPER IP).

## 11) Creating the first song (quick overview)

1. Open the Editor
2. **Songs** → **New**
3. Set the Song ID **exactly matching the REAPER region name**  
e.g. Vergessener Traum
4. Create blocks
5. Click **Save**

→ The song appears automatically in the song list

→ Singer can load it live

## 12) Typical network setups

### Simple

- One computer running REAPER + Lyrics Server
- All devices on the same Wi-Fi

### Stage / live (recommended)

- Dedicated router (offline)
- Main computer via LAN
- Mobile devices via Wi-Fi

 StagePilotPro works **fully offline**.

## 13) Important notes

- **All devices must be on the same network**
- **Update QR codes after every network change**
- **Song order** is controlled exclusively via **region numbers**
- **Song ID must exactly match the region name**
- The Editor does **not** automatically follow song changes in REAPER (intentional, safe editing behavior)
- Songs can be archived by moving their JSON files out of Documents/lyrics/

## 14) Installation philosophy

StagePilotPro is deliberately designed to be:

- **easy to install**
- **license-clear (1 activation)**
- **network-open for many devices**
- **offline-capable**
- **robust for live performance**

Once set up correctly, the system runs stable and reproducible.

